

Update the Software

Every grandMA3 device is delivered with the latest version of the grandMA3 software.

All devices in a network with software versions higher than 1.0 can communicate with each other.


This is to give you information on how to update or downdate the grandMA3 software if needed.

To check which version your device is currently running, use the <u>Version keyword</u> in the command line (does not work with PUs and Nodes).

Check for Updates and Download the Latest Version

To check if there is a new grandMA3 software update:


1. Go to www.malighting.com, click Downloads.



Website malighting.com Downloads


2. Click grandMA3 in the bar on the left.





grandMA3 section

3. Click Software + Release Notes to find the latest software version.



grandMA3 Software section

 ${\bf 4.} \ \ {\bf Click} \ the \ current \ version \ to \ download \ the \ desired \ installation \ package.$





Important:

Every grandMA3 device except with Windows or macOS operating system uses the same software and needs the main installation package grandMA3 Software.

To update the grandMA3 software on a PC or laptop, choose the installation package grandMA3 onPC Software for Windows or grandMA3 Software for macOS.


For network updates via PC or laptop, you also need to download the installation package grandMA3 onPC Software for the connected grandMA3 devices.

The download process starts.

Download an Older Version

To downdate a grandMA3 device to an older software version, e.g. in a permanent installation, follow these steps:


Go to www.malighting.com, click Downloads.



Website malighting.com Downloads


 $2. \ \, \hbox{Click ${\it grandMA3}$ in the bar on the left.}$





grandMA3 section


3. Click Software + Release Notes.



grandMA3 Software section

4. Scroll down and click Archive to find older software versions.






grandMA3 Software archive

5. To open the folder, click the desired version, e.g. Version 1.2.0.2.





grandMA3 Software archive versions

6. Click the desired installer version to download the required installation package.

The download process starts.

Store the Installation Packages

Unlike in grandMA2, all installation packages for grandMA3 software are included in one zip-file.

Extract the entire data from the installation package zip-file.

The folders EFI, ma, and other data included are extracted.

For Windows systems, copy the files from the ma folder into the directory C:\ProgramData\MALightingTechnology\installation_packages.

For macOS systems, copy the files from the ma folder into the directory ~/MALightingTechnology/installation_packages.

To properly update the console, follow all the onscreen instructions that appear during the update.